

## USB Dongle for CAD6

Before connecting the USB Dongle, you should first unlock CAD6 (when installing from CD, this is usually done automatically). After connecting the Dongle, you can start CAD6 which will then be activated by means of the Dongle.

If you activate CAD6 using a USB Dongle, you may install CAD6 on multiple computers (at the office, at home, on the notebook) and use it at any one time on that computer to which the dongle is connected.

Normally, you can simply plug the USB Dongle into a USB port and it will be **automatically detected by the operating system**.

If you are using a Dongle purchased before October 2005, or a CAD6 version before CAD6 Release 2005 Service Pack 1, you will have to install a driver. Below, we will explain the steps necessary to do so.

Using the CAD6 command **"Help > Activation / Dongle"** (or "Help > About..." in OEM versions) you can check if a dongle was detected. If so, its serial number will be displayed.

If you have questions about the installation, please do not hesitate to call us!

## Installation of the Dongle driver (usually not required)


You will usually require administrator rights in order to be able to install the drivers.

**Before you first connect the dongle to the computer**, register the corresponding USB driver with the system. To do so, start the application "INF\_INST.EXE" in the "dongle\drv\_usb\" directory of the CAD6 CD manually.

Now you can connect the dongle. The system will detect the new hardware and a Windows dialog guiding you through the further installation will appear.

Dongles are not included in most standard CAD6 packages but have to be purchased separately. Please also refer to the notes in the Product Information and in the License Agreement.

The dongle driver and the dongle server software can also be downloaded from our website [www.CAD6.com](http://www.CAD6.com) in the "Dongle Software" download section.



Please peel off carefully the dongle attached here!

## Dongle Server for CAD6 (not supported in OEM versions)

If you are using a dongle, you can make it available to all computers in the local area network. The licenses coded into the dongle can then be spread dynamically throughout the network without having to move the dongle around.

All you need to do so is the **free** Dongle Server software that can be installed to any arbitrary network computer. You can download the Dongle Server software together with instructions from [www.CAD6.com](http://www.CAD6.com).